

Camera Calibration portion of Sensor Fusion Calibration

Description: This tutorial will give step-by-step instructions on how the camera of the Drive PX2 is being calibrated through ROS.


What is needed:

- stereo camera
- GMSL Driver: https://github.com/DavidTorresOcana/ros_gmsl_driver
- ROS Kinetic
- Checkboard cardboard cutout

Steps


1. Open a terminal at the directory of the top level of your workspace where the camera driver package is located
2. source the workspace in order to recognize the packages. Run the below command on the terminal

```
>> source ./devel/setup.bash
```




3. Next we will launch the camera driver launch file. Run the below command on the terminal

```
>> roslaunch gmsl_n_cameras gmsl_n_cameras_one.launch
```



4. Next we will launch the lidar launch file for it to run. Run the below command on the terminal

```
>> roslaunch velodyne_pointcloud VLP16_points.launch
```



5. Next run the rostopic list command and find the topic for image_raw.

```
avidia@tegra-ubuntu:~/ros_gmsl_workspace$ rostopic list
/gmsl_camera/port_0/cam_0/camera_info
/gmsl_camera/port_0/cam_0/image_raw
/gmsl_camera/port_0/cam_0/image_raw/compressed
/gmsl_camera/port_0/cam_0/image_raw/compressed/parameter_descriptions
/gmsl_camera/port_0/cam_0/image_raw/compressed/parameter_updates
/gmsl_camera/port_0/cam_0/image_raw/compressedDepth
/gmsl_camera/port_0/cam_0/image_raw/compressedDepth/parameter_descriptions
/gmsl_camera/port_0/cam_0/image_raw/compressedDepth/parameter_updates
/gmsl_camera/port_0/cam_0/image_raw/theora/parameter_descriptions
/gmsl_camera/port_0/cam_0/image_raw/theora/parameter_updates
/gmsl_camera/port_0/cam_0/image_rect
/gmsl_camera/port_0/cam_0/image_rect/compressed
/gmsl_camera/port_0/cam_0/image_rect/compressed/parameter_descriptions
/gmsl_camera/port_0/cam_0/image_rect/compressed/parameter_updates
/gmsl_camera/port_0/cam_0/image_rect/compressedDepth/parameter_descriptions
/gmsl_camera/port_0/cam_0/image_rect/compressedDepth/parameter_updates
/gmsl_camera/port_0/cam_0/image_rect/theora
/gmsl_camera/port_0/cam_0/image_rect/theora/parameter_descriptions
/gmsl_camera/port_0/cam_0/image_rect/theora/parameter_updates
/gmsl_camera/port_0/cam_0/nodelet/parameter_descriptions
/gmsl_camera/port_0/cam_0/nodelet/parameter_updates
/gmsl_camera/port_0/cam_1/image_rect
/gmsl_camera/port_0/cam_1/image_rect/compressed
/gmsl_camera/port_0/cam_1/image_rect/compressed/parameter_descriptions
/gmsl_camera/port_0/cam_1/image_rect/compressed/parameter_updates
/gmsl_camera/port_0/cam_1/image_rect/compressedDepth
/gmsl_camera/port_0/cam_1/image_rect/compressedDepth/parameter_descriptions
/gmsl_camera/port_0/cam_1/image_rect/compressedDepth/parameter_updates
/gmsl_camera/port_0/cam_1/image_rect/theora
/gmsl_camera/port_0/cam_1/image_rect/theora/parameter_descriptions
/gmsl_camera/port_0/cam_1/image_rect/theora/parameter_updates
/gmsl_camera/port_0/cam_1/nodelet/parameter_descriptions
/gmsl_camera/port_0/cam_1/nodelet/parameter_updates
/gmsl_camera/port_0/cam_2/image_rect
/gmsl_camera/port_0/cam_2/image_rect/compressed
/gmsl_camera/port_0/cam_2/image_rect/compressed/parameter_descriptions
/gmsl_camera/port_0/cam_2/image_rect/compressed/parameter_updates
/gmsl_camera/port_0/cam_2/image_rect/compressedDepth
/gmsl_camera/port_0/cam_2/image_rect/compressedDepth/parameter_descriptions
/gmsl_camera/port_0/cam_2/image_rect/compressedDepth/parameter_updates
/gmsl_camera/port_0/cam_2/image_rect/theora
/gmsl_camera/port_0/cam_2/image_rect/theora/parameter_descriptions
/gmsl_camera/port_0/cam_2/image_rect/theora/parameter_updates
/gmsl_camera/port_0/cam_2/nodelet/parameter_descriptions
/gmsl_camera/port_0/cam_2/nodelet/parameter_updates
/gmsl_camera/port_0/cam_3/image_rect
/gmsl_camera/port_0/cam_3/image_rect/compressed
/gmsl_camera/port_0/cam_3/image_rect/compressed/parameter_descriptions
/gmsl_camera/port_0/cam_3/image_rect/compressed/parameter_updates
/gmsl_camera/port_0/cam_3/image_rect/compressedDepth
/gmsl_camera/port_0/cam_3/image_rect/compressedDepth/parameter_descriptions
/gmsl_camera/port_0/cam_3/image_rect/compressedDepth/parameter_updates
/gmsl_camera/port_0/cam_3/image_rect/theora
/gmsl_camera/port_0/cam_3/image_rect/theora/parameter_descriptions
```

6. Once the topic is located, you finally run the camera calibration python script. The example command and parameter description can be seen below.

```
>> rosrn camera_calibration cameracalibrator.py --size 9x6 --square 0.108
```

```
image:=/gmsl_camera/port_0/cam_0/image_raw camera:=/gmsl_camera/port_0/cam_0
```

--size: Indicates the size of the checkboard that will be using. It is described as the cross-sections only and not the actual checker squares. An example, if you have a 10x7 checkboard, you will input a 9x6 into the size parameters since the program does not check the edges but the cross-sections between the squares.

--square: This indicates the size of the individual square used on the check board


--image: This label is used in the calibration script. You will have to map the raw_image to this label

--camera: This label is used in the calibration script. You will have to map the camera topic that is used without the raw_image.

```
nvidia@tegra-ubuntu:~/ros_gmsl_driver_workspace$ clear
nvidia@tegra-ubuntu:~/ros_gmsl_driver_workspace$ rostopic list
/gmsl_camera/port_0/cam_0/camera_info
/gmsl_camera/port_0/cam_0/image_raw
/gmsl_camera/port_0/cam_0/image_raw/compressed
/gmsl_camera/port_0/cam_0/image_raw/compressed/parameter_descriptions
/gmsl_camera/port_0/cam_0/image_raw/compressed/parameter_updates
/gmsl_camera/port_0/cam_0/image_raw/compressedDepth
/gmsl_camera/port_0/cam_0/image_raw/compressedDepth/parameter_descriptions
/gmsl_camera/port_0/cam_0/image_raw/compressedDepth/parameter_updates
/gmsl_camera/port_0/cam_0/image_raw/theora
/gmsl_camera/port_0/cam_0/image_raw/theora/parameter_descriptions
/gmsl_camera/port_0/cam_0/image_raw/theora/parameter_updates
nvidia@tegra-ubuntu:~/ros_gmsl_driver_workspace$
nvidia@tegra-ubuntu:~/ros_gmsl_driver_workspace$ roslaunch camera_calibration cameracalibrator.py --size 9x6 --square 0.108 image
:=/gmsl_camera/port_0/cam_0/image_raw camera:=/gmsl_camera/port_0/cam_0
```

7. Once the running, you will get a screen like the one below.

program is get a screen like



8. Now for our sensor fusion calibration, we will need a rosbag of all the camera and lidar data that can be calibrated to be able to go through the procedure. You will need to record your camera topics, camera_info, and point cloud of your lidar to get through the next steps. See below example

roslaunch camera_calibration cameracalibrator.py --size 9x6 --square 0.108 image
rosbag record -o [fileName to name the bag file] [camera topic to record] [camera info topic to record] [lidar point cloud topic to record]

Example:

```
>> roslaunch camera_calibration cameracalibrator.py --size 9x6 --square 0.108 image
>> rosbag record -o fileName /gmsl_camera/port_0/cam_0/image_raw /gms_camera/port_0/cam_0/camera_info
/velodyne_points
```


Before

```
nvidia@tegra-ubuntu: ~/Desktop
nvidia@tegra-ubuntu:~/Desktop$ rosbag record -o fileName /gmsl_camera/port_0/cam_0/image_raw /gmsl_camera/port_0/cam_0/camera_info /velodyne_points
```


After

```
nvidia@tegra-ubuntu: ~/Desktop
nvidia@tegra-ubuntu:~/Desktop$ rosbag record -o fileName /gmsl_camera/port_0/cam_0/image_raw /gmsl_camera/port_0/cam_0/camera_info /velodyne_points
[ INFO] [1600790898.453113472]: Subscribing to /gmsl_camera/port_0/cam_0/camera_info
[ INFO] [1600790898.470259360]: Subscribing to /gmsl_camera/port_0/cam_0/image_raw
[ INFO] [1600790898.483866304]: Subscribing to /velodyne_points
[ INFO] [1600790898.500625120]: Recording to fileName_2020-09-22-12-08-18.bag.
[ WARN] [1600790898.501109696]: Less than 5 x 1G of space free on disk with fileName_2020-09-22-12-08-18.bag.active.
```


9. Now the program has to get data in order to calibrate the camera. Move the checkerboard image in front of the camera. The program will get data like the images below.



10. Once the program thinks it ready to calibrate, the calibrate button will turn blue indicating calibration is ready. **Please keep calibrating until all the X,Y, Size, and Skew bars below are green colors.** For good lidar data, make sure you get multiple instances of the checkerboard box further away from the camera.



11. Once the parameters are green, press control c and end the rosbag record. Once the rosbag is finished writing, then make sure it is saved to the specific directory your terminal is set to. It will be called a .bag file with the file name you specified in the rosbag record command.



References

- GMSL Camera

Driver

https://github.com/DavidTorresOcana/ros_gmsl_driver

- Calibrating a stereo camera through ROS

http://wiki.ros.org/camera_calibration/Tutorials/StereoCalibration